



SABRE - HOW TO BOOK A SEAT

If seats are not requested, they are allocated automatically once a booking has been ended. Only confirm a booking to a client when a coach and seat number is shown as KK in the SSR in your P4.

To check coach layout and direction of travel, refer to our online seat plans.

Coach and Seat Availability Display entries

Display which coaches are available to book for class of service required for sector 1
4G1*

It is very important that the availability display is checked, as Standard Premier and Business Premier coaches are yield managed, so while on one train a coach maybe Business Premier on another it could be Standard Premier or Standard if it's one of our new trains. If you select a seat in a Standard Premier coach when booking Business Premier your sectors will UC.

Example of coach availability display

```

4G1*«
9F 9008 20SEP TRN COACH MAP
0 - QQS 1 - XPG


COACH  AVAIL  FACILITIES
   1    B0
   2    B2
   3    B0
   4    B2
   5    B4
  14    B0
  15    B9
  16    B9
  17    B0
  18    B1

SEAT MAP UNAVAILABLE:X  PAID BICYCLE:B
FAMILY COMPARTMENT:F  HANDICAPPED FACILITIES:H
UNACCOMPANIED MINOR:U
  
```

Then to display what seats are available in each coach

4G1*/5 to display coach 5

Example seat availability display



Then use the entries below to request specific seats.

SPECIFIC SEATS

Important: - The coach number and seat number must be three characters
Request seat 44 in coach 16 on segment 1

3NSST1/C016S044

Request seats 15 and 16 in coach 4 on segment 2

3NSST2/C004S015016-1.1,2.1

You can also check seat maps from availability:

Entry is

4G*9F9004Y16NOVQQSXPG/O

Or for a specific coach number

4G*9F9004Y16NOVQQSXPG/2/O

Request via seat type instead you can use:

Eurostar seating entry

3NSST//T2

Code	Eurostar seat type
-T2	Club 2 -2 seats facing each other Business Premier & Standard Premier class, with table
-T4	Club 4 and Carre - 4 seats facing each other Business

	Premier & Standard Premier & Standard class, with table
-E1	Solo - Single seat in Business Premier & Standard Premier class, with seat back table
-E2	Duo - 2 seats airline style with seat back tables
W	Window
A	Aisle

Seat Changes

To change a seat that is already allocated, please follow the below procedure.

cancel seats from the P4	41x (for sector 1)
Then check which coach is available for the on board class of service you have chosen	4G1* (for sector 1)
To check which seats are available in the chosen coach	4G1*/10 (for sector 1 coach 10)
Then request your chosen coach and seat number	eg. 3NSST1/c010s011
Receive	
ER	
IR	
Check new seats are KK in the P4	

Overbooking

When overbooked seats are assigned to your booking, you will receive an SSR message warning you of this. As well as only a coach number being displayed e.g C007S000 you will also receive the following SSR message

SSR OTHS 1S 2385 SEGMENT/S OVERBOOKED REQUEST SEAT/S AT CHECK-IN